

Armbian on the Tinkerboard



1

G V V Sharma*

1

CONTENTS

1 OS Image

Wifi on Armbian Bionic desktop mainline kernel 4.14.y

Abstract—This manual provides installing of various softwares in RDP ThinBook Laptop.

1 OS IMAGE

1. Download the Ambian Bionic Desktop OS image (kernel 4.4) from

https://www.armbian.com/ tinkerboard/

and extract the .img file.

2. Burn the image to the sdcard

sudo dd **if**=armbianos.img /dev/ sdX bs=4096 status=progress

where the sdcard location /dev/sdX can be obtained thorugh

sudo fdisk -1

- 3. Inserd the sdcard with the armbian bionic image in the tinkerboard and power on.
- 4. Enter login as **root** and password **1234**. Choose a **username** and **password** for yourself. You should boot into the desktop.
- 5. Set timezone

sudo dpkg-reconfigure tzdata

*The author is with the Department of Electrical Engineering, Indian Institute of Technology, Hyderabad 502285 India e-mail: gadepall@iith.ac.in. All content in this manual is released under GNU GPL. Free and open source.

2 Wifi on Armbian Bionic desktop mainline kernel 4.14.y

Wifi doesn't work properly with the 4.14 Ubuntu desktop due to **Network Manager**. To resolve this do the following.

1. Install wpagui

sudo apt install wpagui

2. Remove network manager

sudo apt remove network-manager

3. Replace interfaces

wget ifaces.txt
cp ifaces /etc/network/
interfaces

4. Open wpa supplicant configuation file

/ etc / wpa _ supplicant /
 wpa _ supplicant . conf

and type the following in the beginning

ctrl_interface=DIR=/var/run/
wpa_supplicant GROUP=netdev
update_config=1

5. Add user to group netdev

sudo usermod -a -G netdev \$USER

6. Check wpa supplicant status

sudo systemctl status wpa_supplicant.service

If active, do nothing. Else start it

sudo systemctl status wpa supplicant.service

7. For giving wpa_supplicant access to wifi network interface.

```
sudo wpa_supplicant -i wlan0 -c

/etc/wpa_supplicant/

wpa_supplicant.conf -D wext
```

8. Open wpa-gui from application menu. Scan for networks. Select your preferred network and enter the password. Connect. In case connection errors are displayed, reboot.